

组网及说明

SVT 2600两节点, OmniStack Software 3.7.10A

配置步骤

SSH登录需要修改密码的OVC, 以具有管理员权限的vCenter Server用户登录, 如administrator@vsphere.local。

执行命令sudo mount -o remount,rw /rroot和sudo touch /rroot/disable-root-ro, 将文件系统修改为读写。

执行命令sudo reboot, 重启OVC。

```
Welcome to Simplivity OmniCube 3.7.10.200
administrator-vsphere@omnicube-ipl72-20:~$ sudo mount -o remount,rw /rroot
administrator-vsphere@omnicube-ipl72-20:~$ sudo touch /rroot/disable-root-ro
administrator-vsphere@omnicube-ipl72-20:~$ sudo reboot
Waiting for the virtual machines that are managed by this omnicube controller to achieve HA compliance. This may take some time. Do NOT exit from the command. If you wish to cancel this operation, issue the command svt-shutdown-cancel from another shell.
```

重启成功后, 使用 命令sudo passwd svtcli命令进行修改svtcli的密码

使用sudo rm /disable-root-ro

使用sudo reboot进行重启

```
Welcome to Simplivity OmniCube 3.7.10.200
administrator-vsphere@omnicube-ipl72-20:~$ sudo passwd svtcli
Enter new UNIX password:
Retype new UNIX password:
passwd: password updated successfully
administrator-vsphere@omnicube-ipl72-20:~$ sudo rm /disable-root-ro
administrator-vsphere@omnicube-ipl72-20:~$ sudo reboot
```

使用新的密码可以进行登录, 能够登录成功

```
? MobaXterm 20.2 ?
(SSSH client, X-server and networking tools)
> SSH session to svtcli@10.12.172.20
? SSH compression : ✓
? SSH-browser : ✓
? X11-forwarding : x (disabled or not supported by server)
? DISPLAY : 10.12.179.226:0.0
> For more info, ctrl+click on help or visit our website

Last login: Thu Jul 2 15:21:17 UTC 2020 from 10.12.179.226 on pts/0
Last failed login: Thu Jul 2 15:32:54 UTC 2020 from 10.12.179.226 on ssh:notty
There was 1 failed login attempt since the last successful login.

Welcome to Simplivity OmniCube 3.7.10.200
Last login: Thu Jul 2 15:21:17 2020 from 10.12.179.226
svtcli@omnicube-ipl72-20:~$
```

配置关键点

注意:

- 需要以具有管理员权限的vCenter Server用户进行操作;
- 操作时不要在目录/rroot下执行命令;
- OVC需要重启