




## 【MVS】思科路由器radius典型组网配置案例

网络相关 韦家宁 2024-07-03 发表

### 组网及说明



本案例采用思科模拟器来模拟思科路由器radius典型组网配置案例，在本案例中，服务器作为AAA服务器，R1路由器作为AAA客户端，采用radius协议来实现路由器的安全登录管理。

### 配置步骤

- 1、按照网络拓扑图配置IP地址。
- 2、在R1开启SSH功能，SSH账号为weijianing，密码weijianing
- 3、在R1配置radius
- 4、在服务器开启AAA功能，并创建radius账号，账号为james，密码james
- 5、在AAA服务器正常时，使用radius账号才能登录R1
- 6、在AAA服务器故障时，使用R1的本地账号才能登录R1


### 配置关键点

```
R1:  
Router>ena  
Router#conf t  
Enter configuration commands, one per line. End with CNTL/Z.  
Router(config)#hos R1  
R1(config)#int f 0/1  
R1(config-if)#ip address 192.168.1.1 255.255.255.0  
R1(config-if)#no shutdown  
R1(config-if)#exit  
R1(config)#int f 0/0  
R1(config-if)#ip address 10.0.0.1 255.255.255.0  
R1(config-if)#no shutdown  
R1(config-if)#exit  
  
R1(config)#ip domain name h3c.com  
R1(config)#aaa new-model  
R1(config)#enable secret weijianing  
  
R1(config)#crypto key generate rsa  
The name for the keys will be: R1.h3c.com  
Choose the size of the key modulus in the range of 360 to 4096 for your  
General Purpose Keys. Choosing a key modulus greater than 512 may take  
a few minutes.  
  
How many bits in the modulus [512]: 1024  
% Generating 1024 bit RSA keys, keys will be non-exportable...[OK]
```

```
R1(config)#username weijianing password weijianing  
R1(config)#ip ssh version 2  
R1(config)#ip ssh time-out 60  
R1(config)#ip ssh authentication-retries 5
```

```
R1(config)#line vty 0 4  
R1(config-line)#transport input ssh  
R1(config-line)#exit
```

PC和服务器填写IP地址，且能相互PING通。



在R1配置radius

```
R1(config)#radius-server host 10.0.0.2  
R1(config)#radius-server key james  
R1(config)#aaa new-model  
R1(config)#aaa authentication login default group radius local  
R1(config)#line vty 0 4  
R1(config-line)#login authentication default  
R1(config-line)#exit
```

在服务器上启用AAA功能，并创建radius账号和密码

The screenshot shows the 'AAA' configuration page in the Server0 interface. The 'Service' section has 'On' selected and 'Radius Port' set to 1645. The 'Network Configuration' section shows a client entry for 'R1' with 'Client Name' and 'Client IP' both empty, 'Server Type' set to 'Radius', and 'Key' set to 'james'. The 'User Setup' section shows a user entry for 'james' with 'Username' and 'Password' both set to 'james'. Red boxes highlight the 'Service' section, the client entry in 'Network Configuration', and the user entry in 'User Setup'.


在PC使用radius账号james能SSH登录R1

```
C:\>ssh -l james 10.0.0.1
Password:
R1>ena
Password:
R1#conf t
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#
```

关闭AAA服务器的AAA功能，R1无法用radius账号james登录

```
C:\>ssh -l james 10.0.0.1
Password:
% Login invalid
```

重新开启AAA服务器的AAA功能，使用radius账号james可以恢复对R1的登录。



```
C:\>ssh -l james 10.0.0.1

Password:
R1>ena
Password:
R1#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
```

至此，思科路由器radius典型组网配置案例已完成。