

## 组网及说明

点到点

## 配置步骤

ikev1主模式：

1、acl

  acl number 3000

    rule 15 permit ip source 1.1.1.1 0 destination 2.2.2.2 0

2、ike安全提议

  ike proposal 1

    encryption-algorithm aes-cbc-128

    authentication-algorithm md5

3、ipsec安全提议

  ipsec transform-set tran1

    esp encryption-algorithm aes-cbc-128

    esp authentication-algorithm sha1

4、ike keychain

  ike keychain key1

    pre-shared-key address 2.2.2.2 255.255.255.0 key simple h3c

5、ike profile

  ike profile pro1

    keychain key1

    local-identity address 1.1.1.1

    match remote identity address 2.2.2.2 255.255.255.0

    proposal 1

6、ipsec策略

  ipsec policy map1 10 isakmp

    transform-set tran1

    security acl 3000

    local-address 1.1.1.1

    remote-address 2.2.2.2

    ike-profile pro1

7、在接口下应用

  interface GigabitEthernet1/0/3

    port link-mode route

    combo enable copper

    ip address 1.1.1.1 255.255.255.0

    ipsec apply policy map1

ikev1野蛮模式：

1、acl

2、ike proposal

3、ike身份信息：

[FW1]ike identity fqdn fwa

4、ike keychain

5、ike profile

  ike profile pro1

    keychain key1

    exchange-mode aggressive

    local-identity fqdn fwa

    match remote identity fqdn fwb

    proposal 1

6、ipsec transform-set

7、ipsec policy

8、接口下应用

ikev2：

1、acl

2、ike proposal

```
3、ikev2 keychain
ikev2 keychain key2
peer p1
address 2.2.2.254 255.255.255.0
identity address 2.2.2.254
pre-shared-key plaintext h3c
4、ikev2 profile
ikev2 profile pro2
authentication-method local pre-share
authentication-method remote pre-share
keychain key2
match remote identity address 2.2.2.254 255.255.255.0
5、ipsec transform-set
6、ipsec policy
7、在接口下应用
```

#### 配置关键点

注意区别即可