

知 Libvirt-bin服务无法启动

zhlliao_6bAvN 2019-06-25 发表

组网及说明

CAS版本: E0306H11

问题描述

重启libvirt-bin服务, 发现无法启动, 有如下报错:

```
root@vnode-04:/var/log# first task --all | less
root@vnode-04:/var/log# service libvirt-bin restart
Stopping libvirtd: OK.
Starting libvirtd: /usr/sbin/libvirtd: error: Unable to obtain pidfile. Check /var/log/messages or run with
out --daemon for more info.
root@vnode-04:/var/log# service libvirt-bin status
libvirtd is not running.
```

过程分析

查看libvirtd的进程:

#ps aux | grep libvirtd

```
root@vnode-04:/var/log#
root@vnode-04:/var/log# ps aux | grep libvirtd
root    59615  0.0  0.0  8156  2220 pts/27   S+   20:44   0:00 grep --color=auto libvirtd
```

查看libvirtd的pid文件:

```
root@vnode-04:/var/log# ls /run/libvirt
libvirt/  libvirtd.pid
root@vnode-04:/var/log# cat /run/libvirtd.pid
```

解决方法

怀疑是libvirtd.pid文件损坏, 移除libvirtd.pid文件重新启动libvirt-bin服务:

```
52586root@vnode-04:/var/log# rm /run/libvirtd.pid
root@vnode-04:/var/log# service libvirt-bin start
Starting libvirtd: OK.
```

重启libvirt-bin服务成功。

附件下载: libvirt-bin服务无法启动.pdf