


知 某局点运维审计系统A2100-G不能telnet管理交换机问题处理经验案例

堡垒机 孟普 2018-04-19 发表

某局点采购了运维审计系统A2100-G，配置后可以正常登录服务器和思科交换机，但是却管理不了华三交换机。

无

1.思科交换机可以正常在运维审计系统telnet登录，但是华三的几台交换机却一直登录检测失败，失败截图如下：




2.查看相关配置





3.SSH登录到堡垒机，从命令行telnet登录交换机是成功的，说明交换机没有做相关的限制



10.52.5.1 - SecureCRT

文件(F) 编辑(E) 查看(V) 选项(O) 传输(T) 脚本(S) 工具(L) 窗口(W) 帮助(H)

输入主机 <Alt+R>

10.200.12.2_JNDZ-BPEC-HR2240-01

10.52.5.1 x

Last login: Wed Apr 18 06:09:36 2018 from 10.53.21.207

Main Menu

1. Date and Time
2. Network Configuration
3. Service Management
4. Administrators
- H. High Availability
- S. System Status
- T. System Tools
- R. System Recovery
- A. Application Server

Enter selection: t

System Tools

1. Ping
2. Traceroute
3. Telnet
4. Forbit root ssh login
0. Return

Enter selection: 3

telnet> login 10.52.54.11

?Invalid command

```
telnet> ?
Commands may be abbreviated.  Commands are:

close      close current connection
logout     forcibly logout remote user and close the connection
display    display operating parameters
mode       try to enter line or character mode ('mode ?' for more)
open       connect to a site
quit       exit telnet
send       transmit special characters ('send ?' for more)
set        set operating parameters ('set ?' for more)
unset      unset operating parameters ('unset ?' for more)
status     print status information
toggle     toggle operating parameters ('toggle ?' for more)
slc        change state of special characters ('slc ?' for more)
z          suspend telnet
!          invoke a subshell
environ    change environment variables ('environ ?' for more)
?          print help information

telnet> open 10.52.54.11
Trying 10.52.54.11...
Connected to 10.52.54.11.
```

4.交换机被telnet登录时是提示login的，但是堡垒机上设置的登录名提示是Username,不一致导致登录失败。

将登录名改为login:后可以正常登录

运维审计系统 - 运维审计系统 - Google Chrome

https://183.1.2.24/manager/server_edit_index.php?id=2&nomenu=1

设备编辑: switch-101.1... (101.102.1.1) 服务列表 密码管理 分配设备组 访问规则 可登录用户

交互提示 [-]

状态 禁用 活动

名称: telnet *

telnet端口: 23 *

连通检测

普通提示符: > *

特权提示符: > *

帐号切换命令: super

切换密码提示: Password: *

登录名提示: login: * ✓

登录密码提示: Password: *

登录成功提示:

额外提示:

额外应答:

跳转登录 [+]

服务选项 [+]

确定 默认填写 返回前页

登录名提示一定要跟设备的提示一模一样，不然会导致管理登录失败。