



与MSR对接时，CISCO 的BGP4+如何配置

BGP

陈丹威

2013-07-25 发表

Cisco实现的BGP4+配置与H3C之前版本配置类似，在bgp全局视图下首先配置BGP4+ peer，然后在ipv6地址族中进行激活。

!

```
router bgp 200
```

```
bgp router-id 65.0.0.1
```

```
bgp log-neighbor-changes
```

```
neighbor 100::2 remote-as 100
```

!

```
address-family ipv4
```

```
no neighbor 100::2 activate
```

```
no auto-summary
```

```
no synchronization
```

```
exit-address-family
```

!

```
address-family ipv6
```

```
neighbor 100::2 activate
```

```
exit-address-family
```

!