



假设原系统主机名为oldname, 新主机名为newname

1). 使用root帐户登录

```
#rcmgr set HOSTNAME
```

2). 编辑/etc/hosts文件,做如下改变:

.....

```
127.0.0.1 localhost
```

```
16.72.0.156 oldname
```

.....

改为:

.....

```
127.0.0.1 localhost
```

```
16.72.0.156 newname
```

.....

3). # cd /sys/conf

```
# cp OLDNAME NEWNAME
```

```
# vi NEWNAME
```

....

```
ident "OLDNAME"
```

....

改为:

.....

```
ident "NEWNAME"
```

.....

4). 编辑/etc/rc.config, 把HOSTNAME从OLDNAME改为NEWNAME

5). # cd /sys/conf

```
# cp OLDNAME.list NEWNAME.list
```

```
# cd /sys
```

```
# mv OLDNAME NEWNAME
```

6) # doconfig -c NEWNAME

```
# cp /vmunix /vmunix.bck
```

```
# cp /sys/NEWNAME/vmunix /vmunix
```

```
# shutdown -r now
```