

知 MSR系列路由器中心设备和分支设备都处于NAT网关后面时分支与中心建立Ipsec隧道功能的配置

陈安【技术大咖】 2007-03-21 发表

MSR系列路由器中心设备和分支设备都处于NAT网关后面时分支与中心建立Ipsec隧道功能的配置


关键字：MSR;NAT;IPSEC;穿越

一、组网需求：

中心设备和分支设备都位于NAT网关后面，分支要与中心设备建立Ipsec连接。

设备清单：MSR系列路由器4台

二、组网图：



三、配置步骤：

适用设备和版本：MSR系列、Version 5.20, Beta 1105后所有版本。

fenzhi配置

```
#  
sysname fenzhi  
#  
ike local-name fenzhi //定义本端IKE的名字  
#  
ike proposal 1  
#  
ike peer zhongxin  
exchange-mode aggressive //采用野蛮模式  
pre-shared-key 123  
id-type name  
remote-name zhongxin  
remote-address 1.1.1.2 //远端地址为nat设备的公网出口地址  
nat traversal //使能nat穿越  
#  
ipsec proposal 1  
#  
ipsec policy zhongxin 1 isakmp  
security acl 3000  
ike-peer zhongxin  
proposal 1  
#  
acl number 3000 //定义要进行加密的数据  
rule 0 permit ip source 10.1.3.0 0.0.0.255 destination 10.1.2.0 0.0.0.255  
rule 1 deny ip  
#  
interface Ethernet2/0  
ip address 192.168.0.2 255.255.255.0  
ipsec policy zhongxin //在接口里应用ipsec policy  
#  
interface LoopBack0  
ip address 10.1.3.1 255.255.255.255  
#  
ip route-static 0.0.0.0 0.0.0.0 192.168.0.1 preference 60  
#
```

NAT_fenzhi 配置

```
#  
sysname NAT_fenzhi  
#  
interface Ethernet2/0  
ip address 192.168.0.1 255.255.255.0  
#  
interface Ethernet2/1  
ip address 1.1.1.1 255.255.255.0  
//使能NAT  
nat outbound 2000  
//开启nat server的功能  
nat server protocol udp global 1.1.1.1 500 inside 192.168.0.2 500  
#  
acl number 2000 //定义进行NAT转换的私网网段  
rule 0 permit source 192.168.0.0 0.0.0.255  
rule 5 deny  
#
```

NAT_zhongxin
<pre> # sysname NAT_zhongxin # acl number 3000 //定义进行NAT转换的私网网段 rule 0 permit ip source 10.1.1.0 0.0.0.255 rule 1 deny ip # interface Ethernet0/0 ip address 1.1.1.2 255.255.255.0 //使能NAT nat outbound 3000 //开启nat server的功能 nat server protocol udp global 1.1.1.2 500 inside 10.1.1.1 500 # interface Ethernet0/1 ip address 10.1.1.2 255.255.255.0 # </pre>
zhongxin 配置
<pre> # sysname zhongxin # ike local-name zhongxin //定义本端IKE 的名字 # ike proposal 1 # ike peer fenzhi exchange-mode aggressive //采用野蛮模式 pre-shared-key 123 id-type name remote-name fenzhi remote-address 1.1.1.1 //远端地址为分支设备公网出口地址 nat traversal //使能nat穿越 # ipsec proposal fenzhi # ipsec policy fenzhi 1 isakmp security acl 3000 ike-peer fenzhi proposal fenzhi # acl number 3000 //定义要进行加密的数据 rule 0 permit ip source 10.1.2.0 0.0.0.255 destination 10.1.3.0 0.0.0.255 rule 1 deny ip # interface Ethernet1/0 ip address 10.1.1.1 255.255.255.0 ipsec policy fenzhi //在接口里应用Ipsec policy # interface LoopBack0 ip address 10.1.2.1 255.255.255.255 # ip route-static 0.0.0.0 0.0.0.0 10.1.1.2 preference 60 # </pre>

四、配置关键点：

- 1) IKE peer远端地址为对端NAT设备的公网出口地址；
- 2) NAT设备上要启用nat server功能，打开UDP 500端口；
- 3) 两个NAT设备的公网口地址要固定。