王思军 2007-03-20 发表

TippingPoint IPS Rollback功能典型配置

TippingPoint "Rollback"功能可以对将系统的TOS恢复到前一次使用的版本,详细配置如下:

1) 进入"System">>"Update">>"TOS DV and Update":



图表 1 TOS and DV Update

2) 进入升级界面,"Step 3">>"previously installed TOS images":

SYSTEM - Update - Manual	Software Update
Step 1:	
Check for DV or TOS updates	from the Invest Management Center and save any new versions to your PC.
Step 2:	
Set current state to "Ready:OF	F
Current State: Ready:OK (rest	<u>t status</u>)
Step 3:	
Make sure the package you do	whoaded is smaller than: 63 MB.
Tip: An unpacked package ma	y require more space than anticipated. To aid, delete one or more of the previously installed TOS images.
Chan de	
Step 4	
Set High Priority Preference	Enabled
Layer-2 Failback:	Enabled
Step 5:	
Select ".pkg" file and press ins	talt 前光 Install
*The installation of TOS upda	tes will reboot the TippingPoint device.

图表 2 Software Update

3) 点击进入,选择"Rollback"。TippingPoint IPS "Rollback"功能可以对将系统的TOS恢复到前面最近 一次所使用的版本.

Product Code: TP1 Serial Number: US0 Current Installed V	-UNITYONE-50 C-3002-4706 Versions:		
Type:	Version:	Package Size:	Function(s):
TOS Software	2.2.4.6519	12 MB	0
Digital Vaccine	2.2.0.6351	956 KB	Rollback
Previous TOS Vers	ions:		
Type:	Version:	Package Size:	Function(s):
TOS Software	2.2.3.6514	12 MB	×
TOC Colleges	2146324	11 MB	92

4) 系统提示"恢复到最近一次的TOS版本",点击"确定"完成操作:

16108	off Internet Explorer
?	This will rollback to the latest version listed in the "Previous TOS Versions" table below. Your system will be rebooted.
8	All changes made since the latest version was installed will be lost.
	The rollback process will take several minutes. Please do not execute other operations until after reboot.
	「頭定」「取消」

图表 3 Rollback