

F1060路由模式典型组网配置案例9 (OSPF STUB与NSSA共存)

设备部署方式 H3C模拟器 韦家宁 2020-03-29 发表

组网及说明



组网说明：

本案例采用H3C HCL模拟器的F1060防火墙来模拟防火墙路由模式的典型部署。为了实现PC之间能够相互通信，因此需要分别在R1、R2、FW1、FW2采用三层互联，同时FW1、FW2采用路由模式，最终实现PC之间能够相互PING通。

配置步骤

1. 按照网络拓扑图正确配置IP地址
2. R1、FW1、FW2、R2之间采用三层互联
3. R1、FW1、FW2、R2之间采用OSPF路由协议实现互通。
4. R1为STUB最终末梢区域
5. R2为NSSA最终末梢区域

配置关键点

R1:

```
<H3C>sys
System View: return to User View with Ctrl+Z.
[H3C]sysname R1
[R1]int loopback 0
[R1-LoopBack0]ip address 1.1.1.1 32
[R1-LoopBack0]quit
[R1]int gi 0/0
[R1-GigabitEthernet0/0]ip address 192.168.1.1 24
[R1-GigabitEthernet0/0]quit
[R1]int gi 0/1
[R1-GigabitEthernet0/1]des <connect to FW1>
[R1-GigabitEthernet0/1]ip address 10.0.0.1 30
[R1-GigabitEthernet0/1]quit
[R1]ospf 1 router-id 1.1.1.1
[R1-ospf-1]area 0.0.0.1
[R1-ospf-1-area-0.0.0.1]network 10.0.0.1 0.0.0.0
[R1-ospf-1-area-0.0.0.1]network 1.1.1.1 0.0.0.0
[R1-ospf-1-area-0.0.0.1]network 192.168.1.0 0.0.0.255
[R1-ospf-1-area-0.0.0.1]stub no-summary
[R1-ospf-1-area-0.0.0.1]quit
[R1-ospf-1]quit
```

R2:

```
<H3C>sys
System View: return to User View with Ctrl+Z.
[H3C]sysname R2
[R2]int loopback 0
[R2-LoopBack0]ip address 4.4.4.4 32
[R2-LoopBack0]quit
[R2]int gi 0/0
[R2-GigabitEthernet0/0]ip address 172.16.1.1 24
[R2-GigabitEthernet0/0]quit
```

```
[R2]int gi 0/1
[R2-GigabitEthernet0/1]ip address 10.0.0.9 30
[R2-GigabitEthernet0/1]quit
[R2]ospf 1 router-id 4.4.4.4
[R2-ospf-1]area 0.0.0.2
[R2-ospf-1-area-0.0.0.2]network 10.0.0.9 0.0.0.0
[R2-ospf-1-area-0.0.0.2]network 4.4.4.4 0.0.0.0
[R2-ospf-1-area-0.0.0.2]network 172.16.1.0 0.0.0.255
[R2-ospf-1-area-0.0.0.2]nssa no-summary
[R2-ospf-1-area-0.0.0.2]quit
[R2-ospf-1]quit
```

```
FW1:
<H3C>sys
System View: return to User View with Ctrl+Z.
[H3C]sysname FW1
[FW1]acl basic 2002
[FW1-acl-ipv4-basic-2002]rule 0 permit source any
[FW1-acl-ipv4-basic-2002]quit
[FW1]
[FW1]zone-pair security source trust destination untrust
[FW1-zone-pair-security-Trust-Untrust]packet-filter 2002
[FW1-zone-pair-security-Trust-Untrust]quit
[FW1]
[FW1]zone-pair security source untrust destination trust
[FW1-zone-pair-security-Untrust-Trust]packet-filter 2002
[FW1-zone-pair-security-Untrust-Trust]quit
[FW1]
[FW1]zone-pair security source trust destination local
[FW1-zone-pair-security-Trust-Local]packet-filter 2002
[FW1-zone-pair-security-Trust-Local]quit
[FW1]
[FW1]zone-pair security source local destination trust
[FW1-zone-pair-security-Local-Trust]packet-filter 2002
[FW1-zone-pair-security-Local-Trust]quit
[FW1]
[FW1]zone-pair security source untrust destination local
[FW1-zone-pair-security-Untrust-Local]packet-filter 2002
[FW1-zone-pair-security-Untrust-Local]quit
[FW1]
[FW1]zone-pair security source local destination untrust
[FW1-zone-pair-security-Local-Untrust]packet-filter 2002
[FW1-zone-pair-security-Local-Untrust]quit
[FW1]
[FW1]zone-pair security source trust destination trust
[FW1-zone-pair-security-Trust-Trust]packet-filter 2002
[FW1-zone-pair-security-Trust-Trust]quit
[FW1]
[FW1]zone-pair security source untrust destination untrust
[FW1-zone-pair-security-Untrust-Untrust]packet-filter 2002
[FW1-zone-pair-security-Untrust-Untrust]quit
[FW1]int loopback 0
[FW1-LoopBack0]ip address 2.2.2.2 32
[FW1-LoopBack0]quit
[FW1]int gi 1/0/2
[FW1-GigabitEthernet1/0/2]des <connect to R1>
[FW1-GigabitEthernet1/0/2]ip address 10.0.0.2 30
[FW1-GigabitEthernet1/0/2]quit
[FW1]int gi 1/0/3
[FW1-GigabitEthernet1/0/3]des <connect to FW2>
[FW1-GigabitEthernet1/0/3]ip address 10.0.0.5 30
[FW1-GigabitEthernet1/0/3]quit
[FW1]security-zone name Untrust
[FW1-security-zone-Untrust]im
```

```
[FW1-security-zone-Untrust]import in
[FW1-security-zone-Untrust]import interface gi
[FW1-security-zone-Untrust]import interface GigabitEthernet 1/0/3
[FW1-security-zone-Untrust]quit
[FW1]security-zone name Trust
[FW1-security-zone-Trust]import interface GigabitEthernet 1/0/2
[FW1-security-zone-Trust]import interface LoopBack 0
[FW1-security-zone-Trust]quit
[FW1]ospf 1 router-id 2.2.2.2
[FW1-ospf-1]area 0.0.0.0
[FW1-ospf-1-area-0.0.0.0]network 10.0.0.5 0.0.0.0
[FW1-ospf-1-area-0.0.0.0]network 2.2.2.2 0.0.0.0
[FW1-ospf-1-area-0.0.0.0]quit
[FW1-ospf-1]area 0.0.0.1
[FW1-ospf-1-area-0.0.0.1]network 10.0.0.2 0.0.0.0
[FW1-ospf-1-area-0.0.0.1]stub
[FW1-ospf-1-area-0.0.0.1]quit
[FW1-ospf-1]quit
```

```
FW2:
<H3C>sys
System View: return to User View with Ctrl+Z.
[H3C]sysname FW2
[FW2]acl basic 2002
[FW2-acl-ipv4-basic-2002]rule 0 permit source any
[FW2-acl-ipv4-basic-2002]quit
[FW2]
[FW2]zone-pair security source trust destination untrust
[FW2-zone-pair-security-Trust-Untrust]packet-filter 2002
[FW2-zone-pair-security-Trust-Untrust]quit
[FW2]
[FW2]zone-pair security source untrust destination trust
[FW2-zone-pair-security-Untrust-Trust]packet-filter 2002
[FW2-zone-pair-security-Untrust-Trust]quit
[FW2]
[FW2]zone-pair security source trust destination local
[FW2-zone-pair-security-Trust-Local]packet-filter 2002
[FW2-zone-pair-security-Trust-Local]quit
[FW2]
[FW2]zone-pair security source local destination trust
[FW2-zone-pair-security-Local-Trust]packet-filter 2002
[FW2-zone-pair-security-Local-Trust]quit
[FW2]
[FW2]zone-pair security source untrust destination local
[FW2-zone-pair-security-Untrust-Local]packet-filter 2002
[FW2-zone-pair-security-Untrust-Local]quit
[FW2]
[FW2]zone-pair security source local destination untrust
[FW2-zone-pair-security-Local-Untrust]packet-filter 2002
[FW2-zone-pair-security-Local-Untrust]quit
[FW2]
[FW2]zone-pair security source trust destination trust
[FW2-zone-pair-security-Trust-Trust]packet-filter 2002
[FW2-zone-pair-security-Trust-Trust]quit
[FW2]
[FW2]zone-pair security source untrust destination untrust
[FW2-zone-pair-security-Untrust-Untrust]packet-filter 2002
[FW2-zone-pair-security-Untrust-Untrust]quit
[FW2]int loopback 0
[FW2-LoopBack0]ip address 3.3.3.3 32
[FW2-LoopBack0]quit
[FW2]int gi 1/0/2
[FW2-GigabitEthernet1/0/2]des <connect to R2>
[FW2-GigabitEthernet1/0/2]ip address 10.0.0.10 30
```

```

[FW2-GigabitEthernet1/0/2]quit
[FW2]int gi 1/0/3
[FW2-GigabitEthernet1/0/3]des <connect to FW1>
[FW2-GigabitEthernet1/0/3]ip address 10.0.0.6 30
[FW2-GigabitEthernet1/0/3]quit
[FW2]security-zone name Untrust
[FW2-security-zone-Untrust]import interface GigabitEthernet 1/0/3
[FW2-security-zone-Untrust]quit
[FW2]security-zone name Trust
[FW2-security-zone-Trust]import interface GigabitEthernet 1/0/2
[FW2-security-zone-Trust]import interface LoopBack 0
[FW2-security-zone-Trust]quit
[FW2]ospf 1 router-id 3.3.3.3
[FW2-ospf-1]area 0.0.0.0
[FW2-ospf-1-area-0.0.0.0]network 10.0.0.6 0.0.0.0
[FW2-ospf-1-area-0.0.0.0]network 3.3.3.3 0.0.0.0
[FW2-ospf-1-area-0.0.0.0]quit
[FW2-ospf-1]area 0.0.0.2
[FW2-ospf-1-area-0.0.0.2]network 10.0.0.10 0.0.0.0
[FW2-ospf-1-area-0.0.0.2]nssa
[FW2-ospf-1-area-0.0.0.2]quit
[FW2-ospf-1]quit

```

测试：

PC都填写IP地址：

The screenshot shows the 'Configure PC_4' interface. At the top, there is a table for interface configuration:

接口	状态	IPv4地址	IPv6地址
G0/0/1	UP	192.168.1.2/24	

Below the table is a '刷新' (Refresh) button. Underneath, there is an 'Interface Management' section with an enable/disable switch set to '启用' (Enabled). The 'IPv4 Configuration' section includes fields for IP address (192.168.1.2), subnet mask (255.255.255.0), and gateway (192.168.1.1), along with a blue '启用' (Enable) button.

The screenshot shows the 'Configure PC_5' interface, similar to the previous one. It features an interface configuration table:

接口	状态	IPv4地址	IPv6地址
G0/0/1	UP	172.16.1.2/24	

Below the table is a '刷新' (Refresh) button. Underneath, there is an 'Interface Management' section with an enable/disable switch set to '启用' (Enabled). The 'IPv4 Configuration' section includes fields for IP address (172.16.1.2), subnet mask (255.255.255.0), and gateway (172.16.1.1), along with a blue '启用' (Enable) button.

PC之间可以相互PING通：

```

<H3C>
<H3C>
<H3C>ping 172.16.1.2
Ping 172.16.1.2 (172.16.1.2): 56 data bytes, press CTRL_C to break
56 bytes from 172.16.1.2: icmp_seq=0 ttl=252 time=3.000 ms
56 bytes from 172.16.1.2: icmp_seq=1 ttl=252 time=3.000 ms
56 bytes from 172.16.1.2: icmp_seq=2 ttl=252 time=4.000 ms
56 bytes from 172.16.1.2: icmp_seq=3 ttl=252 time=3.000 ms
56 bytes from 172.16.1.2: icmp_seq=4 ttl=252 time=3.000 ms

--- Ping statistics for 172.16.1.2 ---
5 packet(s) transmitted, 5 packet(s) received, 0.0% packet loss
round-trip min/avg/max/std-dev = 3.000/3.200/4.000/0.400 ms
<H3C>#Mar 29 09:23:35:581 2020 H3C SHELL/5/SHELL_LOGIN: Console logged in from con0.

```

```

<H3C>
<H3C>
<H3C>ping 192.168.1.2
Ping 192.168.1.2 (192.168.1.2): 56 data bytes, press CTRL_C to break
56 bytes from 192.168.1.2: icmp_seq=0 ttl=252 time=5.000 ms
56 bytes from 192.168.1.2: icmp_seq=1 ttl=252 time=3.000 ms
56 bytes from 192.168.1.2: icmp_seq=2 ttl=252 time=3.000 ms
56 bytes from 192.168.1.2: icmp_seq=3 ttl=252 time=4.000 ms
56 bytes from 192.168.1.2: icmp_seq=4 ttl=252 time=4.000 ms

--- Ping statistics for 192.168.1.2 ---
5 packet(s) transmitted, 5 packet(s) received, 0.0% packet loss
round-trip min/avg/max/std-dev = 3.000/3.800/5.000/0.748 ms
<H3C>#Mar 29 09:23:42:560 2020 H3C SHELL/5/SHELL_LOGIN: Console logged in from con0.

```

分别查看R1、R2、FW1、FW2的OSPF邻居信息：

```

<R1>dis ospf peer
OSPF Process 1 with Router ID 1.1.1.1
      Neighbor Brief Information

Area: 0.0.0.1
Router ID      Address      Pri Dead-Time  State      Interface
2.2.2.2        10.0.0.2     1   36          Full/BDR    GE0/1
<R1>

```

```

[R2]dis ospf peer
OSPF Process 1 with Router ID 4.4.4.4
      Neighbor Brief Information

Area: 0.0.0.2
Router ID      Address      Pri Dead-Time  State      Interface
3.3.3.3        10.0.0.10    1   40          Full/BDR    GE0/1
[R2]

```

```

[FW1]dis ospf peer
OSPF Process 1 with Router ID 2.2.2.2
      Neighbor Brief Information

Area: 0.0.0.0
Router ID      Address      Pri Dead-Time  State      Interface
3.3.3.3        10.0.0.6     1   31          Full/BDR    GE1/0/3

Area: 0.0.0.1
Router ID      Address      Pri Dead-Time  State      Interface
1.1.1.1        10.0.0.1     1   38          Full/DR     GE1/0/2
[FW1]

```

```

[FW2]dis ospf peer
OSPF Process 1 with Router ID 3.3.3.3
      Neighbor Brief Information

Area: 0.0.0.0
Router ID      Address      Pri Dead-Time  State      Interface
2.2.2.2        10.0.0.5     1   35          Full/DR     GE1/0/3

Area: 0.0.0.2
Router ID      Address      Pri Dead-Time  State      Interface
4.4.4.4        10.0.0.9     1   39          Full/DR     GE1/0/2
[FW2]

```

分别查看R1、R2、FW1、FW2的路由表：

```
<R1>dis ip routing-table
Destinations : 24      Routes : 24

Destination/Mask Proto Pre Cost NextHop      Interface
0.0.0.0/0     O_INTEL 10 2    10.0.0.2      GE0/1
0.0.0.0/32    Direct 0   0    127.0.0.1     InLoop0
1.1.1.1/32    Direct 0   0    127.0.0.1     InLoop0
2.2.2.2/32    O_INTEL 10 1    10.0.0.2      GE0/1
3.3.3.3/32    O_INTEL 10 2    10.0.0.2      GE0/1
4.4.4.4/32    O_INTEL 10 3    10.0.0.2      GE0/1
10.0.0.0/30   Direct 0   0    10.0.0.1      GE0/1
10.0.0.0/32    Direct 0   0    10.0.0.1      GE0/1
10.0.0.1/32    Direct 0   0    127.0.0.1     InLoop0
10.0.0.3/32    Direct 0   0    10.0.0.1      GE0/1
10.0.0.4/30    O_INTEL 10 2    10.0.0.2      GE0/1
10.0.0.8/30    O_INTEL 10 3    10.0.0.2      GE0/1
127.0.0.0/8   Direct 0   0    127.0.0.1     InLoop0
127.0.0.0/32   Direct 0   0    127.0.0.1     InLoop0
127.0.0.1/32   Direct 0   0    127.0.0.1     InLoop0
127.255.255.255/32 Direct 0   0    127.0.0.1     InLoop0
172.16.1.0/24  O_INTEL 10 4    10.0.0.2      GE0/1
192.168.1.0/24 Direct 0   0    192.168.1.1    GE0/0
192.168.1.0/32 Direct 0   0    192.168.1.1    GE0/0
192.168.1.1/32 Direct 0   0    127.0.0.1     InLoop0
192.168.1.255/32 Direct 0   0    192.168.1.1    GE0/0
224.0.0.0/4   Direct 0   0    0.0.0.0       NULL0
224.0.0.0/24  Direct 0   0    0.0.0.0       NULL0
255.255.255.255/32 Direct 0   0    127.0.0.1     InLoop0
<R1>
```

```
[R2]dis ip routing-table
Destinations : 23      Routes : 23

Destination/Mask Proto Pre Cost NextHop      Interface
0.0.0.0/32    Direct 0   0    127.0.0.1     InLoop0
1.1.1.1/32    O_INTEL 10 3    10.0.0.10     GE0/1
2.2.2.2/32    O_INTEL 10 2    10.0.0.10     GE0/1
3.3.3.3/32    O_INTEL 10 1    10.0.0.10     GE0/1
4.4.4.4/32    Direct 0   0    127.0.0.1     InLoop0
10.0.0.0/30   O_INTEL 10 3    10.0.0.10     GE0/1
10.0.0.4/30   O_INTEL 10 2    10.0.0.10     GE0/1
10.0.0.8/30   Direct 0   0    10.0.0.9       GE0/1
10.0.0.8/32   Direct 0   0    10.0.0.9       GE0/1
10.0.0.9/32   Direct 0   0    127.0.0.1     InLoop0
10.0.0.11/32  Direct 0   0    10.0.0.9       GE0/1
127.0.0.0/8   Direct 0   0    127.0.0.1     InLoop0
127.0.0.0/32  Direct 0   0    127.0.0.1     InLoop0
127.0.0.1/32  Direct 0   0    127.0.0.1     InLoop0
127.255.255.255/32 Direct 0   0    127.0.0.1     InLoop0
172.16.1.0/24 Direct 0   0    172.16.1.1    GE0/0
172.16.1.0/32 Direct 0   0    172.16.1.1    GE0/0
172.16.1.1/32 Direct 0   0    127.0.0.1     InLoop0
172.16.1.255/32 Direct 0   0    172.16.1.1    GE0/0
192.168.1.0/24 O_INTEL 10 4    10.0.0.10     GE0/1
224.0.0.0/4   Direct 0   0    0.0.0.0       NULL0
224.0.0.0/24  Direct 0   0    0.0.0.0       NULL0
255.255.255.255/32 Direct 0   0    127.0.0.1     InLoop0
[R2]
```

```
[FW1]dis ip routing-table
Destinations : 23      Routes : 23

Destination/Mask Proto Pre Cost NextHop      Interface
0.0.0.0/32    Direct 0   0    127.0.0.1     InLoop0
1.1.1.1/32    O_INTRA 10 1    10.0.0.1      GE1/0/2
2.2.2.2/32    Direct 0   0    127.0.0.1     InLoop0
3.3.3.3/32    O_INTRA 10 1    10.0.0.6      GE1/0/3
4.4.4.4/32    O_INTEL 10 2    10.0.0.6      GE1/0/3
10.0.0.0/30   Direct 0   0    10.0.0.2      GE1/0/2
10.0.0.0/32   Direct 0   0    10.0.0.2      GE1/0/2
10.0.0.2/32   Direct 0   0    127.0.0.1     InLoop0
10.0.0.3/32   Direct 0   0    10.0.0.2      GE1/0/2
10.0.0.4/30   Direct 0   0    10.0.0.5      GE1/0/3
10.0.0.4/32   Direct 0   0    10.0.0.5      GE1/0/3
10.0.0.5/32   Direct 0   0    127.0.0.1     InLoop0
10.0.0.7/32   Direct 0   0    10.0.0.5      GE1/0/3
10.0.0.8/30   O_INTEL 10 2    10.0.0.6      GE1/0/3
127.0.0.0/8   Direct 0   0    127.0.0.1     InLoop0
127.0.0.0/32  Direct 0   0    127.0.0.1     InLoop0
127.0.0.1/32  Direct 0   0    127.0.0.1     InLoop0
127.255.255.255/32 Direct 0   0    127.0.0.1     InLoop0
172.16.1.0/24 O_INTEL 10 3    10.0.0.6      GE1/0/3
192.168.1.0/24 O_INTRA 10 2    10.0.0.1      GE1/0/2
224.0.0.0/4   Direct 0   0    0.0.0.0       NULL0
224.0.0.0/24  Direct 0   0    0.0.0.0       NULL0
255.255.255.255/32 Direct 0   0    127.0.0.1     InLoop0
[FW1]
```

```
[FW2]dis ip routing-table
Destinations : 23      Routes : 23

Destination/Mask Proto Pre Cost     NextHop      Interface
0.0.0.0/32   Direct 0 0          127.0.0.1    InLoop0
1.1.1.1/32   O_INTRA 10 2       10.0.0.5     GE1/0/3
2.2.2.2/32   O_INTRA 10 1       10.0.0.5     GE1/0/3
3.3.3.3/32   Direct 0 0          127.0.0.1    InLoop0
4.4.4.4/32   O_INTRA 10 1       10.0.0.9     GE1/0/2
10.0.0.0/30  O_INTRA 10 2       10.0.0.5     GE1/0/3
10.0.0.4/30  Direct 0 0          10.0.0.6     GE1/0/3
10.0.0.4/32  Direct 0 0          10.0.0.6     GE1/0/3
10.0.0.6/32  Direct 0 0          127.0.0.1    InLoop0
10.0.0.7/32  Direct 0 0          10.0.0.6     GE1/0/3
10.0.0.8/30  Direct 0 0          10.0.0.10    GE1/0/2
10.0.0.8/32  Direct 0 0          10.0.0.10    GE1/0/2
10.0.0.10/32 Direct 0 0          127.0.0.1    InLoop0
10.0.0.11/32 Direct 0 0          10.0.0.10    GE1/0/2
127.0.0.0/8  Direct 0 0          127.0.0.1    InLoop0
127.0.0.0/32 Direct 0 0          127.0.0.1    InLoop0
127.0.0.1/32 Direct 0 0          127.0.0.1    InLoop0
127.255.255.255/32 Direct 0 0  127.0.0.1    InLoop0
172.16.1.0/24 O_INTRA 10 2       10.0.0.9     GE1/0/2
192.168.1.0/24 O_INTRA 10 3       10.0.0.5     GE1/0/3
224.0.0.0/4   Direct 0 0          0.0.0.0      NULL0
224.0.0.0/24  Direct 0 0          0.0.0.0      NULL0
255.255.255.255/32 Direct 0 0  127.0.0.1    InLoop0
[FW2]
```

至此，F1060路由模式典型组网配置案例9（OSPF STUB与NSSA共存）已完成！